

CONDITIONS OF USE BY AUTHORISED PERSONS

The Pest Control Operator must be licensed under state legislation. The Pest Control Operator must notify site supervisor, if any, and workers who come into contact with uncovered treated soil prior to laying the moisture membrane, to wear appropriate personal protective equipment and to observe re-entry requirements. (For personal protective equipment, refer to "SAFETY DIRECTIONS", and for re-entry refer to "PRECAUTIONS RE-ENTRY PERIODS", in the attached leaflet**).

STORAGE, SPILLAGE AND DISPOSAL

Store in closed original container, in a cool, well-ventilated area away from children, animals, food and feedstuffs. **DO NOT** store for prolonged periods in direct sunlight. In case of spillage, confine and absorb spilled product with absorbent material such as sand, clay or cat litter. Dispose of waste as indicated below or according to the Australian Standard AS2507 – Storage and Handling of Pesticides. **DO NOT** allow spilled product to enter sewers, drains, creeks or any other waterways.

For 1L, 2L, 5L, 10L, 20L, 110L, 200L Containers

Triple or preferably pressure rinse containers before disposal. Add rinsings to spray tank. **DO NOT** dispose of undiluted chemicals on-site. If recycling, replace cap and return clean containers to recycler or designated collection point. If not recycling, break, crush or puncture and bury empty containers in a local authority landfill. If no landfill is available, bury the containers below 500 mm in a disposal pit specifically marked and set up for this purpose clear of waterways, vegetation and tree roots. Empty containers and product should not be burnt. **DO NOT** bury waste or surplus product. Dispose of undiluted waste by either dilution or use according to the Directions for Use or returning to the point of purchase in the original container for controlled disposal. Dispose of diluted surplus product by using according to the Directions for Use. **DO NOT** re-use empty container.

For REFILLABLE 1000L containers: Empty contents fully into application equipment. Close all valves and return to point of supply for refill or storage.

SAFETY DIRECTIONS

Poisonous if swallowed. Will damage the eyes and will irritate the skin. Avoid contact with eyes and skin. **REPEATED EXPOSURE MAY CAUSE ALLERGIC DISORDERS. DO NOT** inhale vapour or spray mist. When opening the container and preparing spray, wear cotton overalls buttoned to the neck and wrist, a washable hat, elbow-length **CHEMICAL RESISTANT GLOVES**, face shield or goggles and chemical resistant footwear. When using prepared spray, wear cotton overalls buttoned to the neck and wrist, a washable hat, elbow-length **CHEMICAL RESISTANT GLOVES**, face shield or goggles and chemical resistant footwear. When using in enclosed areas, wear cotton overalls buttoned to the neck and wrist, a washable hat, elbow-length **CHEMICAL RESISTANT GLOVES**, face shield or goggles and chemical resistant footwear. When using in enclosed areas, wear cotton overalls buttoned to the neck and wrist, a washable hat, elbow-length **CHEMICAL RESISTANT GLOVES**, face shield or goggles and chemical resistant footwear and half-face respirator with the combined dust and gas cartridge. If clothing becomes contaminated with product or wet with spray, remove clothing immediately. If product or spray on skin, immediately wash area with soap and water. If product in eyes, wash it out immediately with water. After use and before eating, drinking or smoking, wash hands, arms and face thoroughly with soap and water. Thoroughly ventilate treated areas before reoccupying. After each day's use, wash gloves, face shield or goggles, respirator (if rubber wash with detergent and warm water) and contaminated clothing.

FIRST AID

If poisoning occurs, contact a doctor or Poisons Information Centre (*Ph Australia 13 11 26; New Zealand 0800 764 766*). If swallowed, **DO NOT** induce vomiting. Give a glass of water. If in eyes, hold eyes open, flood with water for at least 15 minutes and see a doctor.

Refer to attached Leaflet for additional GHS Hazard & Precautionary Statements

SAFETY DATA SHEET

Additional information is listed in the Safety Data Sheet, which can be obtained from your supplier or Imtrade Australia Pty Ltd website at www.imtrade.com.au.

CONDITION OF SALE

Imtrade Australia Pty Ltd shall not be liable for any loss, injury, damage or death whether consequential or otherwise whatsoever or howsoever arising whether through negligence or otherwise in connection with the sale supply use or application of this product. The supply of this product is on the express condition that the purchaser does not rely on Imtrade's skill or judgment in purchasing or using the same and every person dealing with this product does so at his own risk absolutely. No representative of Imtrade Australia Pty Ltd has any authority to add to or alter these conditions.

DANGEROUS POISON

KEEP OUT OF REACH OF CHILDREN
READ SAFETY DIRECTIONS BEFORE OPENING OR USING

IMTRADE

BIFENTHRIN ULTRA 400 EC

TERMITICIDE & INSECTICIDE

ACTIVE CONSTITUENT: 400g/L BIFENTHRIN
SOLVENTS: 426g/L LIQUID HYDROCARBONS
100g/L N-METHYL-2-PYRROLIDONE

GROUP 3A INSECTICIDE

For the pre- and post- construction management of subterranean termites in accord with AS3660 and for the control of termites and a range of urban pests. For the protection of timber and timber based products from damage by borers and termites as specified in the Directions for Use table.

Important: Read the attached Leaflet before use.

UN 3352	PYRETHROID PESTICIDE, LIQUID, TOXIC (contains BIFENTHRIN)
	In a Transport Emergency Dial 000 Police or Fire Brigade
PG II	HAZCHEM 2X

APVMA Approval No. 65402/106762



FORM
EC

CONTENTS
1L-1000L



Batch No.
DOM:

IMTRADE
CropScience

17 Ocean St, Kwinana Beach WA 6167
08 9419 0333 | www.imtrade.com.au

DANGEROUS POISON

KEEP OUT OF REACH OF CHILDREN

READ SAFETY DIRECTIONS BEFORE OPENING OR USING



IMTRADE BIFENTHRIN ULTRA 400 EC TERMITICIDE & INSECTICIDE

**ACTIVE CONSTITUENT: 400g/L BIFENTHRIN
SOLVENTS: 426g/L LIQUID HYDROCARBONS
100g/L N-METHYL-2-PYRROLIDONE**

GROUP 3A INSECTICIDE

For the pre- and post- construction management of subterranean termites in accord with AS3660 and for the control of termites and a range of urban pests

For the protection of timber and timber based products from damage by borers and termites as specified in the Directions for Use table

IMPORTANT: RESTRICTED CHEMICAL PRODUCT ONLY TO BE SUPPLIED TO, OR USED BY AN AUTHORISED PERSON

IMPORTANT: READ THIS LEAFLET THOROUGHLY

BEFORE OPENING OR USING THIS PRODUCT

APVMA Approval No: 65402/106762

Imtrade Australia Pty Ltd

ABN 13 090 151 134

17 Ocean Street, Kwinana WA 6167

Tel: 1800 171 799 Fax: 1800 171 788

Web: www.imtrade.com.au

DIRECTIONS FOR USE**RESTRAINTS**

DO NOT use this product at less than indicated label rates.

DO NOT apply to soils if excessively wet or immediately after heavy rain to avoid run-off of the chemical.

DO NOT use in cavity walls (except via certified cavity infill reticulation systems or direct treatment of nest).

PEST	SITUATION	STATE	RATE	CRITICAL COMMENTS
Spiders	External areas & surrounds of domestic, commercial, public & industrial buildings and structures	All States	6.5 - 12.5 mL/ 10L	Use the higher rate in situation where pest pressure is high, when rapid knockdown and/or maximum residual protection is desired. Pay particular attention to protected dark areas such as cracks and crevices, under floors, eaves and other known hiding or resting places. For overall band surface spray, apply as a coarse, low-pressure surface spray to areas where spiders hide, frequent and rest. Spray to the point of run-off using around 5L of spray mixtures per 100m ² and ensuring thorough coverage of the treated surfaces. For crack and crevice treatment use an appropriate solid stream nozzle. For maximum spider control use a two-part treatment. 1. Crack and crevice. 2. Overall band spray of surfaces.
Papernest Wasps	External areas & surrounds of domestic, commercial, public & industrial buildings and structures	All States	12.5 mL/ 10L	Apply prepared emulsion to the point of run-off directly to the papernest ensuring thorough and even coverage. When all adult wasps have been knocked-down the nest may be safely removed from the structure.

PEST	SITUATION	STATE	RATE	CRITICAL COMMENTS
Ants, Cockroaches, Mosquitoes, Fleas, Flies, Ticks (excluding the paralysis tick <i>Ixodes holocyclus</i>) (Adults & Nymphs)	External area & surrounds of domestic, commercial, public & industrial buildings and structures	All States	12.5 - 25 mL/ 10L	<p>On non-porous surfaces apply as a coarse spray at the rate of 1L emulsion per 20m². When treating non-porous surfaces do not exceed the point of run-off. On porous surfaces or use through power equipment, spray at the rate of 1L of emulsion per 10m². When treating porous surfaces do not exceed the point of run-off. Use the higher rate in situations where pest pressure is high, when rapid knockdown and/or maximum residual protection is desired. The lower rate may be used for follow-up treatments. To control ants apply to trails and nests. Repeat as necessary.</p> <p>To control fleas and ticks apply prepared emulsion to outside surfaces of buildings and surrounds including but not limited to foundations, verandahs, window frames, eaves, patios, garages, pet housing, soil, turf, trunks or woody ornamentals or other areas where pests congregate or have been seen.</p> <p>To control flies and mosquitoes apply prepared emulsion to surfaces where insects rest or harbour. Reapply as necessary.</p> <p>For perimeter treatments apply the prepared emulsion to a band of soil or vegetation two to three metres wide around and adjacent to the structure. Also treat the foundation of the structure to a height of approximately one metre. Use a spray volume of 5 to 10L per 100m². Higher volumes of water may be needed if organic matter is present or foliage is dense.</p>
Subterranean Termites	Domestic, public, commercial & industrial areas	All States, except Tas	Refer to Table A	Refer to Table B.

TABLE A: Imtrade Bifenthrin Ultra 400 EC Termiticide and Insecticide use rates for management of SUBTERRANEAN TERMITES

SITUATION	All areas SOUTH of the Tropic of Capricorn (except Tas)		All areas NORTH of the Tropic Capricorn	
	RATE	Expected Protection Period*	RATE	Expected Protection Period*
Pre-Construction Barriers Under slabs and under suspended floors with less than 400 mm crawl space	250 mL/100L	At least 10 years	375 mL/100L	5 years
			250 mL/100L (Note 1)	4 years
	125 mL/100L	10 years	187.5 mL/100L (Note 1)	3 years
			125 mL/100L (Note 1)	2 years
Perimeter Barriers For new and existing buildings	250 mL/100L	At least 10 years	375 mL/100L	5 years
	125 mL/100L	10 years	250 mL/100L	4 years
	62.5 mL/100L	3 years	187.5 mL/100L	3 years
			125 mL/100L	2 years
Post-Construction Barriers Under slabs and under suspended floors with less than 400 mm crawl space	250 mL/100L	At least 10 years	375 mL/100L	5 years
			250 mL/100L	4 years
	125 mL/100L	10 years	187.5 mL/100L	3 years
			125 mL/100L	2 years
Reticulation Systems Perimeter and/or service penetration treatment only	250L/100L	At least 10 years	375 mL/100L	5 years
	125 mL/100L	10 years	250mL/100L	4 years
	62.5 mL/100L	3 years	187.5 mL/100L	3 years
			125 mL/100L	2 years
Reticulation Systems Cavity infill & footing barriers	125 mL/100L	5 years	250 mL/100L	2 years

TABLE A: Intrade Bifenthrin Ultra 400 EC Termiticide and Insecticide use rates for management of SUBTERRANEAN TERMITES (continued)

SITUATION	All areas SOUTH of the Tropic of Capricorn (except Tas)		All areas NORTH of the Tropic Capricorn	
	RATE	Expected Protection Period*	RATE	Expected Protection Period*
Protection of Poles & Fence Posts	125 mL/100L	10 years	375 mL/100L	5 years
			250 mL/100L	4 years
			187.5 mL/100L	3 years
Nest Eradication	125 mL/100L	Not applicable	125 mL/100L	Not applicable
<p>Note 1: This rate must be used in conjunction with a certified reticulation system that is capable of distributing the Termiticide & Insecticide emulsion according to the product label and the Australian Standard AS3660 Series.</p>				
<p>* The need for treatment is to be determined as a result of at least an annual inspection, or more frequently in high-risk area, by a qualified Pest Control Operator.</p>				
<p>The actual protection period will depend on the termite hazard, climate, soil conditions and rate of Termiticide use.</p>				

TABLE B: CRITICAL COMMENTS for use against SUBTERRANEAN TERMITES

SITUATION	CRITICAL COMMENTS
<p>Pre-Construction Barriers Under slabs for protection of new buildings</p>	<ul style="list-style-type: none"> • Apply with suitable application equipment to form a complete and continuous chemical barrier (both vertical and horizontal) under the slab. The formation of the barrier may require a combination of conventional open wand application and soil trenching and/or rodding applications. Recommended rod spacing should be between 150 and 300 mm, as per soil type. For additional information refer to "CRITICAL APPLICATION DETAILS" on this label and the Australian Standard AS3660 Series. • An external perimeter barrier (both horizontal and vertical) is an essential part of termite protection and must be installed at the completion of the building. Refer to "Perimeter Barriers" below, for further details. • Chemical barriers that have been disturbed by construction, excavation and/or landscaping activities will need to be reapplied to restore continuity of the barrier.

TABLE B: CRITICAL COMMENTS for use against SUBTERRANEAN TERMITES (continued)

SITUATION	CRITICAL COMMENTS
<p>Pre-Construction Barriers Under suspended floors</p>	<ul style="list-style-type: none"> • For area beneath suspended floors that have inadequate access (e.g. less than 400mm clearance), the entire sub-floor area should be treated as a continuous horizontal barrier, which completely abuts an internal vertical barrier around any substructure walls. Ideally, this operation should be done during construction of the building while access is more readily available. • For areas beneath suspended floors, which have adequate access (e.g. more than 400mm clearance), install perimeter barriers around each individual pier, stump, service penetration and substructure wall. • An external perimeter barrier (both horizontal and vertical) is an essential part of termite protection and must be installed at the completion of the building. Refer to "Perimeter Barriers" in this leaflet, for further details.
<p>Perimeter Barriers For new and existing buildings</p>	<ul style="list-style-type: none"> • Perimeter barriers (both horizontal and vertical, external and where required, internal and sub-floor) are an essential part of termite protection and must be installed at the completion of the building. Perimeter barriers should be installed around slabs, piers, substructure walls and external penetrations points. • Apply with suitable application equipment to form a continuous chemical barrier (both vertical and horizontal) around the structure and to a depth reaching 80mm below the top of the footings, where appropriate. The formation of the barrier may require a combination of several application techniques, including soil trenching and/or rodding and open wand applications. • Chemical barriers that have been disturbed by construction, excavation and/or landscaping activities will need to be reapplied to restore continuity of the barrier.
<p>Post-Construction Barrier Treatments For the protection of existing buildings</p>	<ul style="list-style-type: none"> • Apply with suitable application equipment to form a continuous chemical barrier (both vertical and horizontal) around and under the structure with particular emphasis on known infestation areas. The formation of the barrier may require a combination of several application techniques, including soil rodding, trenching, open wand applications and sub-slab injections. • Chemical barriers beneath concrete slabs and paths will require concrete drilling. Recommended drill hole spacings are between 150 and 300mm. To enhance soil distribution use a lateral dispersion tip on the injector and up to 10L of emulsion per linear metre. To ensure formation of a continuous barrier, holes should be drilled no more than 150mm from walls or expansion joints. • For areas beneath suspended floors that have inadequate access (e.g. less than 400mm clearance), the entire sub-floor area should be treated as a continuous horizontal barrier, which completely abuts an internal vertical barrier around any substructure walls. Otherwise, install perimeter barriers around each individual pier, stump, penetration point and substructure walls. • Chemical barriers that have been disturbed by construction, excavation and/or landscaping activities will need to be reapplied to restore continuity of the barrier.

TABLE B: CRITICAL COMMENTS for use against SUBTERRANEAN TERMITES (continued)

SITUATION	CRITICAL COMMENTS
<p>Reticulation Systems Perimeter and/or service penetration treatment only</p>	<ul style="list-style-type: none"> • Imtrade Bifenthrin Ultra 400 EC Termiticide & Insecticide must be used through a certified reticulation system to form and replenish perimeter barriers around buildings and service penetrations. The system must be installed according to the manufacturer's specifications and be capable of distributing the Termiticide emulsion according to the product label and the Australian Standard AS3660 Series. • Perimeter barriers consist of a horizontal barrier abutting a vertical barrier, which must reach down to the top of the footing. • Delivery pipes must be placed in such a position to ensure that the requirements for both horizontal and vertical barriers as specified in the Australian Standard AS3660 Series are met. Special attention must also be afforded to the positioning of the delivery pipes to ensure that the resultant termiticidal barriers are continuous and complete. • Apply the prepared Termiticide emulsion by pumping through the system according to the manufacturer's specifications. Use a minimum delivery volume of 100L of emulsion per m3 of soil. This equates to a delivery volume of 5L of emulsion per linear metre for a vertical barrier 300mm x 150mm in dimension. • Pre-Construction – For use in conjunction with full soil treatment horizontal barriers only: Apply the diluted emulsion through the perimeter reticulation system as specified above. Follow instructions for Pre-Construction horizontal barrier formation.
<p>Reticulation Systems Cavity infill & footing barriers</p>	<ul style="list-style-type: none"> • Imtrade Bifenthrin Ultra 400 EC Termiticide & Insecticide must be used through a certified reticulation system to form and replenish cavity infill and footing barriers. The system must be installed according to the manufacturer's specifications and be capable of distributing the Termiticide emulsion according to the product label and the Australian Standard AS3660 Series. • Delivery pipes must be placed in such a position to ensure that the requirements for both horizontal and vertical barriers as specified in the Australian Standard AS3660 Series are met. Special attention must also be afforded to the positioning of the delivery pipes to ensure that the resultant termiticidal barriers are continuous and complete. • Apply the prepared Termiticide emulsion by pumping through the system according to the manufacturer's specifications with delivery volume of 2L of emulsion per linear metre of delivery pipe. • Note: where this system is to be installed at the pre-construction stage, a full under slab pre-construction barrier, applied by either open wand application or suitably certified reticulation system, is also recommended. • The recommended rate of application is 2L of emulsion per linear metre, which equates to 2L of emulsion per 0.0068m³ or approximately 7L of sand. Should the volume of fill in the wall cavity deviate from 7L (0.17m x 0.04m x 1m = 0.0068m³) per linear metre of wall cavity, then the amount of Imtrade Bifenthrin Ultra 400 EC Termiticide & Insecticide emulsion applied per linear metre of wall cavity should be adjusted accordingly. As a guide, the target bifenthrin loading of treated sand/soil in a cavity infill situation is 110 mg/kg South of the Tropic of Capricorn and 220 mg/kg North of the Tropic of Capricorn. • To facilitate more even distribution of Imtrade Bifenthrin Ultra 400 EC Termiticide & Insecticide emulsion in the wall cavity, ensure that the fill is evenly compacted at the time of installation. To further enhance distribution saturation of the sand/soil in the infill is recommended at the time of treatment.

TABLE B: CRITICAL COMMENTS for use against SUBTERRANEAN TERMITES (continued)

SITUATION	CRITICAL COMMENTS
Protection of Service Poles & Fence Posts	<ul style="list-style-type: none"> • Create a continuous Termiticide barrier 450mm deep and 150mm wide around the pole or post by soil injection or rodding. For new poles and posts, treat backfill and the bottom of the hole. Use 100L of emulsion per m³ of soil. • Regular inspections should be undertaken to determine when and if treatment is necessary. If disturbance of the barrier has occurred, retreatment of the area affected will be required. • Posts and poles may also be drilled and injected with spray solution. • Note: For existing poles and posts, it is impractical to treat the full depth and underneath of such poles and posts and therefore the possibility of future termite attack from below the treated area cannot be ruled out.
Eradication of Termite Nest	<ul style="list-style-type: none"> • Locate nest and flood with insecticide emulsion. Trees, poles, posts and stumps containing nests may require drilling prior to treatment with Termiticide emulsion. The purpose of drilling is to ensure the Termiticide emulsion is distributed throughout the entire nest. Drill holes in live trees should be sealed with an appropriate caulking compound after injection.

Note: The Termiticide barrier provided by this product has a finite life. This together with the recommendation to undertake annual inspection must be stated on the durable notice required by the BCA, B1.3 (j) (ii).

NOT TO BE USED FOR ANY PURPOSE, OR IN ANY MANNER, CONTRARY TO THIS LABEL UNLESS AUTHORISED UNDER APPROPRIATE LEGISLATION.

DIRECTIONS FOR USE – TIMBER

RESTRAINTS

DO NOT use treated timber or boards in situations other than those deemed Hazard Class H1 or H2.

Situations	Pest	State	Rate	Critical Comments
Lyctid susceptible sawn and round timbers for treatment by vacuum or vacuum pressure impregnation use in Hazard Class H1	Powder Post Beetle (<i>Lyctus</i> spp.)	All States	3.75 mL/100kg of timber	<ol style="list-style-type: none"> 1. Calculate uptake of suitable diluent (e.g. organic solvents or water) per 100kg of timber. 2. Add the appropriate amount of Imtrade Bifenthrin Ultra 400 EC Termiticide & Insecticide to the diluent to achieve recommended loadings. 3. Apply to timber through vacuum or vacuum pressure treatment equipment to ensure compliance with AS1604. 4. The minimum individual piece retention as specified in AS1604 is 0.0012% active ingredient mass/mass.

DIRECTIONS FOR USE – TIMBER (continued)

Situations	Pest	State	Rate	Critical Comments
Sawn and round timbers for treatment by vacuum or vacuum pressure impregnation use in Hazard Class H2	All Termites (including <i>Mastotermes darwiniensis</i> & <i>Coptotermes acinaciformis</i>)	All States	12.5 mL/100kg of timber	<ol style="list-style-type: none"> 1. Calculate uptake of suitable diluent (e.g. organic solvents or water) per 100kg of timber. 2. Add the appropriate amount of Imtrade Bifenthrin Ultra 400 EC Termiticide & Insecticide to the diluent to achieve recommended loadings. 3. Apply to timber through vacuum or vacuum pressure treatment equipment to ensure compliance with AS1604. 4. The minimum individual piece retention as specified in AS1604 is 0.0047% active ingredient mass/mass.
	Softwoods only: As above plus Furniture Beetle (<i>Anobium punctatum</i>), European House Borer (<i>Hylotrupes bajulus</i>)			
Framing timbers for surface spray application or dipping Hazard Class H2 with no exposure to sunlight	All Termites EXCLUDING <i>Mastotermes darwiniensis</i>	All areas South of the Tropic of Capricorn	0.47mL/m ² of surface area	<ol style="list-style-type: none"> 1. Calculate uptake of suitable diluent (e.g. organic solvents or water) per 100kg of timber. 2. Calculate the surface area of 1m³ or product to treat. 3. Add the appropriate amount of Imtrade Bifenthrin Ultra 400 EC Termiticide & Insecticide to the diluent to achieve recommended loadings. 4. Apply to timber through a spray system or by dripping to ensure compliance with the recommended rates. 5. The minimum individual piece retention is 18µg active ingredient per cm².
	Softwoods only: As above plus Furniture Beetle (<i>Anobium punctatum</i>), European House Borer (<i>Hylotrupes bajulus</i>)			
Softwood particle & Strand based boards in Hazard Class H2	All Termites (including <i>Mastotermes darwiniensis</i> & <i>Coptotermes acinaciformis</i>) & Timber Beetles	All States	0.14 mL/kg of dry fibre	Add sufficient Imtrade Bifenthrin Ultra 400 EC Termiticide & Insecticide into the glue to achieve a retention of 0.0047% active ingredient mass/mass in the finished board. Alternatively particles on strands can be treated prior to manufacture. When Imtrade Bifenthrin Ultra 400 EC Termiticide & Insecticide is added to the glue mix, the pH of the finished mix must not exceed 9.5.
Processing & Manufacture of softwood plywood in Hazard Class H2			62.5 mL/m ² dry veneer	<ol style="list-style-type: none"> 1. Calculate uptake of solution by veneers. 2. Dilute Imtrade Bifenthrin Ultra 400 EC Termiticide & Insecticide as required to ensure loading of 0.005% active ingredient mass/mass in the veneers. 3. Following the manufacture of the plywood panel the loading of bifenthrin in the panel should be a minimum of 0.004% mass/mass.

DIRECTIONS FOR USE – TIMBER (continued)

Situations	Pest	State	Rate	Critical Comments
Glueline treatment of softwood plywood and LVL (2.5mm thick veneer) for use in Hazard Class H2	All Termites EXCLUDING <i>Mastotermes darwiniensis</i>	All areas South of the Tropic of Capricorn	62.5 mL/m ³ in the glueline	<ol style="list-style-type: none"> 1. Calculate the usage of glue per cubic metre of panel. 2. Add Imtrade Bifenthrin Ultra 400 EC Termiticide & Insecticide to the glue during preparation of the mix. 3. Following the manufacture of the plywood panel the loading of bifenthrin in the panel should be a minimum of:
			All States	250 mL/m ³ in the glueline
		125 mL/m ³ in the glueline and 50 mL in the faces		<p>Glue Line Treatment</p> <ul style="list-style-type: none"> • Calculate the usage of glue per cubic metre of panel. • Add Imtrade Bifenthrin Ultra 400 EC Termiticide & Insecticide to the glue during preparation of the mix. • Following the manufacture of the plywood panel the loading of Imtrade Bifenthrin Ultra 400 EC Termiticide & Insecticide in the panel should be a minimum of 0.004% active ingredient mass/mass. <p>Face Treatment</p> <ul style="list-style-type: none"> • Calculate the uptake of solution by faces. • Add Imtrade Bifenthrin Ultra 400 EC Termiticide & Insecticide to the working solution. • Following the manufacture of the plywood panel the loading of Imtrade Bifenthrin Ultra 400 EC Termiticide & Insecticide in the panel should be a minimum of 0.0042% active ingredient mass/mass.

DIRECTIONS FOR USE – TIMBER (continued)

Situations	Pest	State	Rate	Critical Comments
Glueline treatment of softwood plywood and LVL (3.2mm thick veneer) for use in Hazard Class H2	All Termites EXCLUDING <i>Mastotermes darwiniensis</i>	All areas South of the Tropic of Capricorn	62.5 mL/m ³ in the glueline and 12.5 mL in the faces	<p>Glue Line Treatment</p> <ul style="list-style-type: none"> • Calculate the usage of glue per cubic metre of panel. • Add Imtrade Bifenthrin Ultra 400 EC Termiticide & Insecticide to the glue during preparation of the mix. • Following the manufacture of the plywood panel the loading of Imtrade Bifenthrin Ultra 400 EC Termiticide & Insecticide in the panel should be a minimum of 0.0021% active ingredient mass/mass. <p>Face Treatment</p> <ul style="list-style-type: none"> • Calculate the uptake of solution by faces. • Add Imtrade Bifenthrin Ultra 400 EC Termiticide & Insecticide to the working solution. • Following the manufacture of the plywood panel the loading of Imtrade Bifenthrin Ultra 400 EC Termiticide & Insecticide in the panel should be a minimum of 0.001% active ingredient mass/mass.

NOT TO BE USED FOR ANY PURPOSE, OR IN ANY MANNER, CONTRARY TO THIS LABEL UNLESS AUTHORISED UNDER APPROPRIATE LEGISLATION.

CONDITION OF USE BY AUTHORISED PERSONS

The pest control operator must be licensed under state legislation. The pest operator must notify site supervisor, if any, and workers who come into contact with uncovered treated soil prior to laying the moisture membrane, to wear appropriate personal protective equipment and to observe re-entry requirements. (For personal protective equipment, refer to "SAFETY DIRECTIONS", and for re-entry, refer to "PRECAUTION: RE-ENTRY PERIODS", below **).

GENERAL INSTRUCTIONS

Urban pest control:

Imtrade Bifenthrin Ultra 400 EC Termiticide & Insecticide is a powerful knockdown and residual pesticide. Ants, cockroaches, fleas, flies, mosquitoes, spiders, ticks and wasps are controlled by direct contact with spray and also by residual action as they come in to contact with treated surfaces.

Termites:

The use of Imtrade Bifenthrin Ultra 400 EC Termiticide & Insecticide will help prevent and control subterranean termite infestations in and around building and structures when used in accordance with the Australian Standard AS3660 Series, Termite Management. A dilute termiticidal emulsion must be adequately dispersed into the soil to establish a barrier between the building and subterranean termites in the soil. The purpose of a termite barrier is to prevent concealed termite entry into the building. The biology and behaviour of the termite species involved should be considered by the pest control operator in determining which control measures are most appropriate to control and prevent termite infestations.

Termites – Timber:

The use of Imtrade Bifenthrin Ultra 400 EC Termiticide & Insecticide to both timber and timber based products as specified in the Directions for Use Table will protect treated products from damage by subterranean termites. In most situations protection will be afforded against all termite species including *Coptotermes acinaciformis* and *Mastotermes darwiniensis*. The treatment should be conducted in accordance with Australian Standard AS1604 Series and the minimum retention of bifenthrin in end use products should be 0.0047% active ingredient mass/mass

INSECTICIDE RESISTANCE WARNING

GROUP 3A INSECTICIDE

For insecticide resistance management Imtrade Bifenthrin Ultra 400 EC Termiticide & Insecticide is a Group 3A Insecticide. Some naturally occurring insect biotypes resistant to Imtrade Bifenthrin Ultra 400 EC Termiticide & Insecticide and other Group 3A Insecticide may exist through normal genetic variability in any insect population. The resistant individuals can eventually dominate the insect population if Imtrade Bifenthrin Ultra 400 EC Termiticide & Insecticide or other Group 3A insecticides are used repeatedly. The effectiveness of Imtrade Bifenthrin Ultra 400 EC Termiticide & Insecticide on resistant individuals could be significantly reduced. Since occurrence of resistant individuals is difficult to detect prior to use, Imtrade Australia Pty Ltd accepts no liability for any losses that may result from the failure of Imtrade Bifenthrin Ultra 400 EC Termiticide & Insecticide to control resistant insects.

Imtrade Bifenthrin Ultra 400 EC Termiticide & Insecticide may be subject to specific resistance management strategies. For further information, contact your local supplier, Imtrade Australia representatives or local agricultural department agronomist.

MIXING – Termiticidal Uses

Add the required quantity Imtrade Bifenthrin Ultra 400 EC Termiticide & Insecticide to water in the spray tank and mix thoroughly. Maintain agitation during both mixing and application. To facilitate even application of the Termiticide emulsion over the area to be treated, the addition of a marker dye at label rate is recommended. On hard to wet soil the penetration of the Termiticide emulsion may be improved by the addition of a soil surfactant at label rate.

MIXING – Timber

Add the required quantity of Imtrade Bifenthrin Ultra 400 EC Termiticide & Insecticide to diluent in the holding tank or glue mixer and mix thoroughly. Maintain agitation during both mixing and application.

CRITICAL APPLICATION DETAILS – TERMITICIDAL USES

The application of Imtrade Bifenthrin Ultra 400 EC Termiticide & Insecticide to form both horizontal and vertical chemical barriers must be in accordance with the Australian Standard AS3660 Series. For treatment of new and existing buildings, both horizontal and vertical barriers may be required, around and under the building. External perimeter barriers and where required, internal perimeter barriers, are an essential part of this treatment. The purpose of a chemical termite soil barrier is to provide a continuous, no gap barrier between the building and the termite colony. It is therefore essential that the pest control operator is familiar with the construction details of the building. For further details, refer to the "Horizontal Barrier Treatments" and "Vertical Barrier Treatments" statements in this leaflet and to the Australian Standard AS3660 Series.

Horizontal Barrier Treatments:

Use 5L of emulsion per m² of soil. Apply the Termiticide emulsion evenly to the soil surface area to ensure the provision of a continuous barrier with no gaps. To minimise drift, use low pressure, high volume spray equipment delivering large coarse droplets. On impervious soils where the application of 5L/m² would cause excessive run-off, the application volume may be reduced provided the concentration of the emulsion is increased by a corresponding amount. For example, the volume of applied concentrate must remain constant at 25, 50 or 75 mL/m² depending on the location and the situation. **DO NOT** apply emulsion volumes below 2L/m². In situations where the soil surface is very dry and conditions are conducive to rapid drying, the areas to be treated should be moistened prior to the Termiticide application. It is important to note that when applying a horizontal barrier to the perimeter of a building or structure the chemical barrier is deemed to have a depth of 80mm. In situations where the emulsion will not readily wet the soil to the required depth, loosen soil to a depth of 80mm by 150mm wide and apply 1.5L of emulsion per lineal metre.

Vertical Barrier Treatments:

To install vertical barrier use a minimum of 100L of emulsion per m³ of soil. Vertical barriers must be a minimum of 150mm wide, extend down to 80mm below the top of the footing and be complete and continuous. Vertical barriers can be installed by trenching and treating the soil as it is backfilled, by soil rodding or by the use of certified reticulation systems, as described in the Australian Standard AS3660 Series. The preferred method of installing a vertical barrier treatment is either by trenching and treating the soil as it is backfilled or by delivery via a certified reticulation system. When using the soil rodding method to establish a vertical barrier the distance between rod spacing should be as per the following table. To improve soil penetration, the soil should be loosened to depth of 150mm.

Soil type	Rod Spacing (mm)
Heavy clay	150
Clay loams	200
Loams	250
Sands	300

Perimeter Barrier Treatments:

Perimeter barrier consists of horizontal barrier at least 150mm wide adjoining a vertical barrier of at least 150mm in width. A perimeter barrier must completely surround all buildings, pipes, piers and service penetrations. In buildings with suspended floors with greater than 400mm crawl space, perimeter barriers should be installed to surround piers, stumps and service penetrations and completely about all substructure walls. To ensure provision of a continuous barrier use a minimum of 100L of emulsion per m³ of soil. This equates to a delivery volume of 5L of emulsion per linear metre for a 300mm vertical barrier, or 10L of emulsion per linear meter for a 600mm vertical barrier. Termites may gain access behind engaged piers against single brick walls unless the soil is treated on both sides of the wall down to the footing.

Post-Construction under Slab Treatments:

For concrete slabs, the emulsion needs to be injected through pre-drilled holes through the slab, at intervals between 150mm and 300mm. The following table shows the recommended hole spacing and recommended volume of spray solution required per hole, depending the soil type.

Soil type	Hole Spacing (mm)	Litres per hole
Heavy clay	150	1.5
Clay loams	200	2
Loams	250	2.5
Sands	300	3

Application equipment used to inject Imtrade Bifenthrin Ultra 400 EC Termiticide & Insecticide through pre-drilled holes in an interior situation must be in good working order, free of any leaks and the injector must have tip shut-off to prevent nozzle dripping. Lateral dispersion tips are recommended. Drill holes must be resealed following injection of the Imtrade Bifenthrin Ultra 400 EC Termiticide & Insecticide emulsion. The decision and/or need for drilling concrete floor slabs should only be made after thorough inspection of the building. The degree of termite activity should also be taken into consideration.

Treatment in Conjunction with Physical Barriers:

In situations where the termite protection system is to consist of a combination of both physical and chemical barriers, each certified system must be installed according to the relevant and appropriate product specification and the Australian Standard AS3660 Series.

Reticulation systems:

Imtrade Bifenthrin Ultra 400 EC Termiticide & Insecticide can be used through reticulation systems to form horizontal and vertical barriers under and around structures and all service penetrations. The reticulation system must be certified and be capable of distributing the Termiticide emulsion according to the product label and Australian Standard AS3660 Series. In situations using reticulations system to form barriers around perimeter and /or service penetrations only, a full pre-construction soil applied Imtrade Bifenthrin Ultra 400 EC Termiticide & Insecticide horizontal barrier is recommended. It is the responsibility of the builder and all relevant sub-contractors to ensure that all termite barrier systems are installed in accordance with the relevant product installation directions and the Australian Standard AS3660 Series.

Service Requirements:

Service requirements are to be determined as a result of least an annual inspection by a licensed Pest Control Operator. More frequent inspections may be required in high-risk termite areas. In determining the need for service, factors such as local termite pressure, breaches of the barrier and Termiticide longevity should be considered.

Subterranean termites are on occasions capable of bridging termite barriers and therefore regular inspections, as detailed in the Australian Standard AS4349.3 will significantly increase the probability of detection of termite activity before any damage or costly repairs are required.

Several factors contribute longevity of the termite treatment and must be considered when evaluating the need for retreatment. The actual protection period will depend on the termite hazard, climate, soil conditions and rate of Termiticide used. Refer to Table A for the expected protection periods provided.

PRECAUTIONS AND RE-ENTRY PERIOD

DO NOT spray into the air or directly on humans, pets or animals. Avoid contact with food, food utensils or preparation surfaces.

RE-ENTRY PERIOD

Pre-construction:

DO NOT allow entry into uncovered treated areas until the spray has dried. When prior entry is necessary, wear cotton overalls buttoned to the neck, wrist and elbow-length PVC, neoprene or nitrile gloves and chemical resistant footwear. Clothing must be laundered after each day's use.

Post-Construction and urban pest control:

DO NOT allow people and pets to enter treated areas until the spray has dried. When prior entry is necessary, wear cotton overalls buttoned to the neck, wrist and elbow-length PVC, neoprene or nitrile gloves and chemical resistant footwear. Clothing must be laundered after each day's use.

PROTECTION OF WILDLIFE, FISH, CRUSTACEANS AND THE ENVIRONMENT

Dangerous to fish and aquatic organisms.

DO NOT contaminate dams, rivers, streams or waterways or drains with product or used containers.

PROTECTION OF PETS AND LIVESTOCK

Before spraying, remove animals and pets from the areas to be treated. Cover or remove any open food and water containers. Cover or remove fish ponds, aquariums etc before spraying.

STORAGE, SPILLAGE AND DISPOSAL

Store in closed original container, in a cool, well-ventilated area away from children, animals, food and feedstuffs. **DO NOT** store for prolonged periods in direct sunlight. In case of spillage, confine and absorb spilled product with absorbent material such as sand, clay or cat litter. Dispose of waste as indicated below or according to the Australian Standard AS2507 – Storage and Handling of Pesticides. **DO NOT** allow spilled product to enter sewers, drains, creeks or any other waterways.

For 1L, 2L, 5L, 10L, 20L, 110L, 200L Containers

Triple or preferably pressure rinse containers before disposal. Add rinsings to spray tank. **DO NOT** dispose of undiluted chemicals on-site. If recycling, replace cap and return clean containers to recycler or designated collection point. If not recycling, break, crush or puncture and bury empty containers in a local authority landfill. If no landfill is available, bury the containers below 500 mm in a disposal pit specifically marked and set up for this purpose clear of waterways, vegetation and tree roots. Empty containers and product should not be burnt. **DO NOT** bury waste or surplus product. Dispose of undiluted waste by either dilution or use according to the Directions for Use or returning to the point of purchase in the original container for controlled disposal. Dispose of diluted surplus product by using according to the Directions for Use. **DO NOT** re-use empty container.

For REFILLABLE 1000L containers: Empty contents fully into application equipment. Close all valves and return to point of supply for refill or storage.

SAFETY DIRECTIONS

Poisonous if swallowed. Will damage the eyes and will irritate the skin. Avoid contact with eyes and skin. **REPEATED EXPOSURE MAY CAUSE ALLERGIC DISORDERS. DO NOT** inhale vapour or spray mist. When opening the container and preparing spray, wear cotton overalls buttoned to the neck and wrist, a washable hat, elbow-length **CHEMICAL RESISTANT GLOVES**, face shield or goggles and chemical resistant footwear. When using prepared spray, wear cotton overalls buttoned to the neck and wrist, a washable hat, elbow-length **CHEMICAL RESISTANT GLOVES**, face shield or goggles and chemical resistant footwear. When using in enclosed areas, wear cotton overalls buttoned to the neck and wrist, a washable hat, elbow-length **CHEMICAL RESISTANT GLOVES**, face shield or goggles and chemical resistant footwear and half-face respirator with the combined dust and gas cartridge. If clothing becomes contaminated with product or wet with spray, remove clothing immediately. If product or spray on skin, immediately wash area with soap and water. If product in eyes, wash it out immediately with water. After use and before eating, drinking or smoking, wash hands, arms and face thoroughly with soap and water. Thoroughly ventilate treated areas before reoccupying. After each day's use, wash gloves, face shield or goggles, respirator (if rubber wash with detergent and warm water) and contaminated clothing.

FIRST AID

If poisoning occurs, contact a doctor or Poisons Information Centre (Ph Australia 13 11 26; New Zealand 0800 764 766). If swallowed, **DO NOT** induce vomiting. Give a glass of water. If in eyes, hold eyes open, flood with water for at least 15 minutes and see a doctor.

Additional GHS Hazard & Precautionary Statements

● Toxic if inhaled; ● May cause respiratory irritation; ● Suspected of causing cancer; ● May damage fertility or the unborn child; ● Causes damage to organs through prolonged or repeated exposure; ● Very toxic to aquatic life with long lasting effects; ● **DO NOT** breathe fumes, mists, vapours or spray; ● **DO NOT** get on clothing; ● Wash contacted areas thoroughly after handling; ● **DO NOT** eat, drink or smoke when using this product; ● Use only outdoors or in a well-ventilated area; ● In case of inadequate ventilation wear respiratory protection; ● Rinse mouth; ● Remove all contaminated clothing immediately; ● **IF SWALLOWED:** Immediately call a POISON CENTRE or doctor; ● **IF INHALED:** Remove victim to fresh air and keep at rest in a position comfortable for breathing; ● If skin irritation occurs: Get medical advice; ● If eye irritation persists: Get medical advice; ● Collect spillage; ● In case of fire, note the following: Water fog or fine spray is the preferred medium for large fires. Try to contain spills, minimise spillage entering drains or water courses; ● Store locked up; ● Store in a dry place.

SAFETY DATA SHEET

Additional information is listed in the Safety Data Sheet, which can be obtained from your supplier or Imtrade Australia Pty Ltd website at www.imtrade.com.au

CONDITION OF SALE

Imtrade Australia Pty Ltd shall not be liable for any loss, injury, damage or death whether consequential or otherwise whatsoever or howsoever arising whether through negligence or otherwise in connection with the sale supply use or application of this product. The supply of this product is on the express condition that the purchaser does not rely on Imtrade's skill or judgment in purchasing or using the same and every person dealing with this product does so at his own risk absolutely. No representative of Imtrade Australia Pty Ltd has any authority to add to or alter these conditions.

UN 3352	PYRETHROID PESTICIDE, LIQUID, TOXIC (contains BIFENTHRIN)
In a Transport Emergency Dial 000 Police or Fire Brigade	
PG II	HAZCHEM 2X

APVMA Approval No. 65402/106762

